Firmware Download / Program Setup

Manual



Application Model. HN800

HN-120

HN-101

HN-102

HN-100E

HI-GHD

HI-QHD



Firmware Download

NOVATEK



Manual

1. Please prepare the following items.



HDMI CABLE



USB CABLE

2. Connect the target board and the DOWNLOAD TOOL to the PC with the prepared cable.





- 3. Double-click the Writer_20160505.exe file located in [C: ₩ Program Files ₩ EasyWriter].
- ① Click the **[Load File]** tab.

② Please select the firmware file to be loaded. If you can not see the file, please change the file format (T) to **Bank Switch(126k, 256k)**.





4. If you change the file format (T) to Bank Switch (126k, 256k), you can see four xx.h00 ~ xx.h03 files, please open one of these files.





5. 1 Click the Load File tab.

② The **xx.hex** file is created as shown below.





6. When the firmware download is **completed**, the process is as shown below.



In Progress



Completed



[Error Message] If the firmware download is in error, it will appear as below.





Program Setup NOVATEK

High Quality Display Solution

Manual

NOVATEK Program Setup_

 $1. \ \textcircled{\ } \text{Decompress the } \textbf{[EasyWriter_20150312.7z]} \ \text{file from the two attached files.}$

② Double-click the [EasyWriter_20150312.exe] file to run it.

	이름	수정한 날짜	유형	크기
	BasyWriter_20150312	2016-08-14 오후	파일 폴더	
1	BasyWriter_20150312.7z	2015-03-13 오전	압축(7Z) 파일	9,672KB
	yWriter_20150312			► ← EasyWriter_20
	공유 대상 ▼ 새 폴더			
	이름	수정한 날짜	유형	크기
2	SasyWriter_20150312.exe	2015-03-13 오전	응용 프로그램	18,644KB





2. Please proceed in the following order.









NOVATEK Program Setup

3. ① Please extract the [Writer_20150505.zip] file from the two attached files and check the [Writer_20150505.exe] file.

② Copy the [Writer_20150505.exe] file to the **[C: ₩ Program Files ₩ EasyWriter]** folder.

③ Please run [Writer_20150505.exe] as **an administrator**.





NOVATEK Program Setup

4. ① After executing the tool, select Option> Setup ISP Tool from the menu.

② When the Setup Form window appears, check **FTDI**.

③ Click the **Confirm Change** button.





NOVATEK Program Setup

5. ① After executing the Tool, select Option> WP Pin Select from the menu.

② Please mark it all the places you specified below.

③ Click the **Save** button.



